

Block 16 - Ampère's Law and Magnetomotive Force (MMF)

Student Group

First Name	Surname	Matrikel Nr.

Table of Contents

Block 16 - Ampère's Law and Magnetomotive Force (MMF)	2
<i>Learning objectives</i>	2
<i>Preparation at Home</i>	2
<i>90-minute plan</i>	2
<i>Conceptual overview</i>	2
<i>Core content</i>	2
<i>Generalization of the Magnetic Field Strength</i>	2
Notice:	3
Notice:	4
Recap of the fieldline images	5
longitudinal coil	5
toroidal coil	5
<i>Common pitfalls</i>	6
<i>Exercises</i>	6
Task 3.2.3 Magnetic Potential Difference	6
Exercise E1 Magnetic Voltage (written test, approx. 6 % of a 120-minute written test, SS2021)	7
Exercise E2 Magnetic Potential (written test, approx. 8 % of a 120-minute written test, SS2024)	8
Exercise E1 Fields of an coax Cable (written test, approx. 12 % of a 120-minute written test, SS2024)	10
<i>Embedded resources</i>	11

Block 16 - Ampère's Law and Magnetomotive Force (MMF)

Learning objectives

After this 90-minute block, you can

- ...

Preparation at Home

Well, again

- read through the present chapter and write down anything you did not understand.
- Also here, there are some clips for more clarification under 'Embedded resources' (check the text above/below, sometimes only part of the clip is interesting).

For checking your understanding please do the following exercises:

- ...

90-minute plan

1. Warm-up (x min):
 1.
2. Core concepts & derivations (x min):
 1. ...
3. Practice (x min): ...
4. Wrap-up (x min): Summary box; common pitfalls checklist.

Conceptual overview

1. ...

Core content

Generalization of the Magnetic Field Strength

So far, only the rotational symmetric problem of a single wire was considered in formula. I.e a current I and the length l of a magnetic field line around the wire was given to calculate the magnetic field strength H :

$$\begin{aligned} \quad H_{\varphi} &= \frac{I}{2 \pi r} \quad \Leftrightarrow \\ \quad I &= H_{\varphi} \cdot s \quad \quad \quad | \quad \text{applies only to the long, straight conductor} \end{aligned}$$

Now, this shall be generalized. For this purpose, we will look back at the electric field.

For the electric field strength E of a capacitor with two plates at a distance of s and the potential difference U holds:

$$\begin{aligned} U &= E \cdot s \quad \quad | \quad \text{applies to plate capacitor only} \end{aligned}$$

In words: The potential difference is given by adding up the field strength along the path of a probe from one plate to the other.

This was extended to the voltage between two points 1 and 2 . Additionally, we know by Kirchhoff's voltage law that the voltage on a closed path is "0".

$$\begin{aligned} U_{12} &= \int_1^2 \vec{E} \cdot d\vec{s} \quad U = \oint \vec{E} \cdot d\vec{s} = 0 \end{aligned}$$

We can now try to look for similarities. Also for the magnetic field, the magnitude of the field strength is summed up along a path to arrive at another field-describing quantity.

Because of the similarity the so-called **magnetic potential difference V_m** between point 1 and 2 is introduced:

$$\begin{aligned} V_m &= H \cdot s \quad \quad | \quad \text{applies to rotational symmetric problems only} \end{aligned}$$

$$\boxed{V_m = V_{m, 12} = \int_1^2 \vec{H} \cdot d\vec{s} \quad V_m = \oint \vec{H} \cdot d\vec{s} = \theta}$$

We need to take a closer look here. Any closed path in the static electric field leads to a potential difference of $U = \oint \vec{E} \cdot d\vec{s} = 0$.

BUT: closed paths in the static magnetic field leads to a magnetic potential difference which is **not mandatorily** 0 ! $V_m = \oint \vec{H} \cdot d\vec{s} = \theta$

Another new quantity is introduced: the **magnetic voltage θ** :

1. The magnetic voltage θ is the magnetic potential difference on a closed path.
2. Since the magnetic voltage θ is valid for exactly one turn along our single wire, θ is also equal to the current through the wire:

$$\begin{aligned} \theta &= H \cdot s = I \quad \quad | \quad \text{applies only to the long, straight conductor} \end{aligned}$$

3. The magnetic potential difference can take a fraction or a multiple of one turn and is therefore **not mandatorily** equal to I .
4. The magnetic voltage is generalized in the following box.

Notice:

The path integral of the magnetic field strength along an arbitrary closed path is equal to the free currents (= current density) through the surface enclosed by the path.

The magnetic voltage θ (and therefore the current) is the cause of the magnetic field strength.

This leads to the **Ampere's Circuital Law**

$$\oint_{\gamma} \vec{H} \cdot d\vec{s} = \theta$$

The magnetic voltage θ can be given as

- $\theta = I$ for a single conductor
- $\theta = N \cdot I$ for a coil
- $\theta = \sum_n I_n$ for multiple conductors
- $\theta = \int_A \vec{S} \cdot d\vec{A}$ for any spatial distribution (see [block15](#))

The unit of the magnetic voltage θ is **Ampere** (or **Ampere-turns**).


In the english literature the magnetic voltage is called **Magnetomotive force**

Notice:

$\oint_{\gamma} \vec{S} \cdot d\vec{A}$ and $\oint_{\gamma} \vec{A} \cdot d\vec{s}$ in $\oint_{\gamma} \vec{H} \cdot d\vec{s} = \theta = \int_A \vec{S} \cdot d\vec{A}$ build a right-hand system.

1. Once the thumb of the right hand is pointing along $\oint_{\gamma} \vec{A} \cdot d\vec{s}$, the fingers of the right hand show the correct direction for $\oint_{\gamma} \vec{S} \cdot d\vec{A}$ for positive $\oint_{\gamma} \vec{H} \cdot d\vec{s}$ and $\int_A \vec{S} \cdot d\vec{A}$
2. Currents into the direction of the right hand's thumb count positive. Currents antiparallel to it count negative.

Fig. 1: Right hand rule



Recap of the fieldline images

longitudinal coil

Fig. 2: Magnetic field in a longitudinal coil

A longitudinal coil can be seen in [figure 2](#). The magnetic field in a toroidal coil is often considered as homogenous in the inner volume, when the length l is much larger than the diameter: $l \gg d$. With a given number N of windings, the magnetic field strength H is

$$\begin{aligned} \theta &= H \cdot l = N \cdot I \\ \boxed{H} &= \frac{N \cdot I}{l} \end{aligned}$$

longitudinal coil

toroidal coil

Fig. 3: Magnetic field in a toroidal coil

A toroidal coil has a donut-like setup. This can be seen in [figure 3](#).

The toroidal coil is often defined by:

- The minor radius r : The radius of the circular cross-section of the coil.
- The major radius R : The distance from the center of the entire toroid (the center of the hole) to the center of the circular cross-section of the coil.

For reasons of symmetry, it shall get clear that the field lines form concentric circles. Also the magnetic field strength H in a toroidal coil is often considered as homogenous, when $R \gg r$. With a given number N of windings, the magnetic field strength H is

$$\theta = H \cdot 2\pi R = N \cdot I$$
$$H = \frac{N \cdot I}{2\pi R} \quad \bigg| \text{toroidal coil}$$

Common pitfalls


- ...

Exercises

Task 3.2.3 Magnetic Potential Difference

Fig. 3: different trajectories around current-carrying conductors
Result 6)

$$V_{(r, \theta)} = \frac{\mu_0 I}{2\pi} \ln\left(\frac{r}{r_0}\right) = \frac{2 \cdot 10^{-7} \cdot 4.5}{2\pi} \ln\left(\frac{r}{r_0}\right) = -2.5 \cdot 10^{-7} \ln\left(\frac{r}{r_0}\right) \text{ V}$$



Given are the adjacent closed trajectories in the magnetic field of current-carrying conductors (see figure 3). Let $I_1 = 2\text{ A}$ and $I_2 = 4.5\text{ A}$ be valid.

In each case, the magnetic potential difference V_{m} along the drawn path is sought.

Path

- The magnetic potential difference is given as the **sum of the current through the area within a closed path**.
- The direction of the current and the path have to be considered with the righthand rule.

Exercise E1 Magnetic Voltage


(written test, approx. 6 % of a 120-minute written test, SS2021)

The following images show cross-sections of electrical cables.

A closed path is shown as a dashed line. The magnetic voltage $\oint \vec{H} \cdot d\vec{s}$ on these paths shall be analyzed.

The following values are given for the currents:

- $I_1 = 5 \text{ A}$ $I_2 = 1 \text{ A}$ $I_3 = 1 \text{ A}$ $I_4 = 4 \text{ A}$
- $I_1 = 5 \text{ A}$
 - $I_2 = 1 \text{ A}$
 - $I_3 = 1 \text{ A}$
 - $I_4 = 4 \text{ A}$



Specify which magnetic voltages $\theta_{(1)}$, $\theta_{(2)}$, and $\theta_{(3)}$ result. Note the direction of the path in each case!

Path

For the resulting current the direction of the path has to be considered with the right-hand rule:

- $I_{(1)} = +I_2 - I_1 - I_3 \quad \rightarrow \quad \theta_{(1)} = 2 \text{ A} - 5 \text{ A} - 1 \text{ A}$
- $I_{(2)} = +I_3 + I_4 - I_1 \quad \rightarrow \quad \theta_{(2)} = 1 \text{ A} + 4 \text{ A} - 5 \text{ A}$
- $I_{(3)} = +I_3 - I_4 - I_2 \quad \rightarrow \quad \theta_{(3)} = 1 \text{ A} - 4 \text{ A} - 2 \text{ A}$

Exercise E2 Magnetic Potential

(written test, approx. 8 % of a 120-minute written test, SS2024)


Calculate the magnetic potential difference V_{m} for the following paths as shown by the solid lines.

Dotted lines are only for there for symmetry aspects!

The wires conduct the following currents:

- $|I_1| = 2 \text{ A}$
- $|I_2| = 5 \text{ A}$
- $|I_3| = 11 \text{ A}$
- $|I_4| = 7 \text{ A}$

Pay attention to the signs of the currents (given by the diagrams) and of the results!



Result

Based on the right-hand rule and the part of a full revolution the following results:

1. Task: $+I_1 - I_2 = -3 \text{ A}$
2. Task: $+\frac{1}{4} I_3 = \frac{11}{4} \text{ A}$ (it does not matter which way the path goes from the startpoint to the endpoint, as long as it has the same direction and number of revolutions)
3. Task: $-\frac{1}{4} I_1 = -0.5 \text{ A}$
4. Task: $+2 \cdot I_2 - 1 \cdot I_3 = -1 \text{ A}$

Exercise E1 Fields of an coax Cable**(written test, approx. 12 % of a 120-minute written test, SS2024)**

2. With the graph of the magnitude of the electric field strength E (in V/m) and the magnitude of the magnetic field strength H (in A/m) as a function of the radial distance r (in mm) from the center of the cable, the diagram shows the results for a coaxial cable with an inner conductor of radius $a = 0.1 \text{ mm}$ and an outer conductor of inner radius $b = 0.55 \text{ mm}$ and outer radius $c = 0.6 \text{ mm}$. The diagram is a schematic representation of the cable cross-section and the fields. The inner conductor is a solid circle with radius a and current $I_i = +3.3 \text{ mA}$ flowing into the page. The outer conductor is a hollow cylinder with inner radius b and outer radius c , and current $I_o = -10 \text{ nC}$ flowing out of the page. The electric field E is shown as a vector field pointing radially outwards from the inner conductor. The magnetic field H is shown as a vector field pointing tangentially around the inner conductor. The diagram is a schematic representation of the cable cross-section and the fields. The inner conductor is a solid circle with radius a and current $I_i = +3.3 \text{ mA}$ flowing into the page. The outer conductor is a hollow cylinder with inner radius b and outer radius c , and current $I_o = -10 \text{ nC}$ flowing out of the page. The electric field E is shown as a vector field pointing radially outwards from the inner conductor. The magnetic field H is shown as a vector field pointing tangentially around the inner conductor.

- Path
- Inner conductor: $+3.3 \text{ mA}$, $+10 \text{ nC}$ (current into the plane of the diagram)
 - Outer conductor: -3.3 mA , 0 nC (current out of the plane of diagram)
 - for $(0.1 \text{ mm} | 0)$: $E_{\text{r i}} = 528 \text{ V/m}$
 - for $(0.55 \text{ mm} | 0)$: $E_{\text{r o}} = 6.985 \text{ V/m}$

The magnitude of the electric displacement field D can be calculated by: $\oint D \cdot d\mathbf{r} = Q_{\text{enc}}$

In general, the E -field is proportional to $\frac{1}{r}$ for the situation between both conductors.

For the E -field, one can use the surface of the cylinder as a Gaussian surface. This leads to: $E(r) = \frac{Q_{\text{enc}}}{\epsilon_0 \cdot A} = \frac{Q_{\text{enc}}}{\epsilon_0 \cdot 2\pi r \cdot L}$

This is proportional to the area within this radius. Therefore, the formula $H =$

So, we get for $E_{\text{r i}}$ at $r = 0.1 \text{ mm}$, and $E_{\text{r o}}$ at $r = 0.55 \text{ mm}$.

For r within the outer conductor one also gets a linear proportionality with a $\begin{aligned} D_{\text{r i}} &= \frac{Q_{\text{enc}}}{2\pi r \cdot L} = \frac{10 \cdot 10^{-9} \text{ C}}{2\pi \cdot 0.1 \cdot 10^{-3} \text{ m} \cdot 0.5 \cdot 10^{-3} \text{ m}} \\ D_{\text{r o}} &= \frac{Q_{\text{enc}}}{2\pi r \cdot L} = \frac{10 \cdot 10^{-9} \text{ C}}{2\pi \cdot 0.55 \cdot 10^{-3} \text{ m} \cdot 0.5 \cdot 10^{-3} \text{ m}} \end{aligned}$

Hint: For the direction, one has to consider the sign of the enclosed charge. By this, we see that the D -field is positive.

But here, again only the magnitude was questioned!

.. What is the magnitude of the magnetic field strength H at $(0.1 \text{ mm} | 0)$ and $(0.55 \text{ mm} | 0)$?

Path

The magnitude of the magnetic field strength H can be calculated by: $H = \frac{I}{2\pi r}$

So, we get for $H_{\text{r i}}$ at $r = 0.1 \text{ mm}$, and $H_{\text{r o}}$ at $r = 0.55$

~mm | 0)\$:

$$\begin{aligned} H_{\text{i}} &= \frac{I}{2 \pi \cdot r_{\text{i}}} \quad \&= \frac{+3.3 \text{ A}}{2 \pi \cdot \{0.1 \cdot 10^{-3} \text{ m}\}} \quad H_{\text{o}} &= \frac{I}{2 \pi \cdot r_{\text{o}}} \quad \&= \frac{+3.3 \text{ A}}{2 \pi \cdot \{0.55 \cdot 10^{-3} \text{ m}\}} \end{aligned}$$

Hint: For the direction, one has to consider the right-hand rule. By this, we see that the H -field on the right side points downwards.

Therefore, the sign of the H -field is negative.

But here, only the magnitude was questioned!

Embedded resources

Explanation (video): ...

From:

<https://wiki.mexle.te.hs-heilbronn.de/> - **MEXLE Wiki**

Permanent link:

https://wiki.mexle.te.hs-heilbronn.de/electrical_engineering_and_electronics_1/block16?rev=1763896899

Last update: **2025/11/23 12:21**

